

## Recover the Linux root password

### Resolution

1. Boot server from the installation CD.
2. Then select any installation method or Rescue System.
3. At the first installation screen when selecting language, press ctrl-alt-f2 to open a virtual console.

Note: If you selected Rescue System, select your keyboard language and then a Rescue Login prompt should appear. Login as root.

4. Type

```
fdisk -l
```

to list the partitions. Locate the Linux root partition.

5. Type

```
mount /dev/sda4 /mnt
```

(replace sda4 with the device name for the Linux root partition identified in the previous step).

6. Run

```
mount -o bind /dev /mnt/dev
```

to make the device files available (this is needed for access to the urandom device which may be used by the passwd command below).

7. Enter

```
chroot /mnt
```

8. Now enter

```
passwd root
```

and reset the root password.

9. Type

```
exit
```

to leave the chroot environment.

10. Reboot the system.

Eindeutige ID: #1088

Verfasser: n/a

Letzte Änderung: 2018-12-24 09:11